

LPIC-1 101-500 – Lesson 9

101.1 Determine and configure hardware settings



The *sysfs* (*/sys*) virtual filesystem

- */sys* is a virtual filesystem and just like */proc* and */dev* exists only in memory
- Contains information about system devices, device drivers as well as communication buses like **pci**, **usb**, **scsi** etc.
- Can be used for some basic configuration
- **\$ mount -t sysfs sysfs /sys #**
mount **sysfs** on */sys*
- **\$ df -hTa | grep sysfs # display**
sysfs
sysfs sysfs 0 0 0 - */sys*

The *proc* (*/proc*) filesystem

- **/proc** is another virtual filesystem and as such exists only in memory
- The files and directories under it are created on startup and during operation of the system
- Provides information on running services
- Provides information on system devices
- Provides many other useful information about the system
- **\$ mount -t proc proc /proc # mount the /proc filesystem**
- **\$ df -hTa | grep \/proc\$ # display proc**

proc	proc	0	0	0	- /proc
------	------	---	---	---	---------

The *udev* device manager and the */dev* directory

- The */dev* directory hosts all the system devices:
- **\$ ls -laR /dev**
- The files and directories inside */dev* are dynamic but in some legacy systems they are static
- In modern systems devices are dynamically created using the **udev** device manager
- Under **udev** the */dev* directory exists as a **devtmpfs** virtual filesystem
- **\$ df -hTa | grep \/dev\$ # display /dev**

udev	devtmpfs	3.9G	0	3.9G	0%	/dev
------	----------	------	---	------	----	------

The D-Bus service

- **D-Bus** (Desktop Bus) is an Inter-Process communication and RPC mechanism for UNIX and Linux systems
- It allows the communication between various programs in the same system
- Originally used by graphical environments it is now an essential part of most Linux systems (either with GUI or not)
- In modern systems it is tightly coupled with **systemd**



USB Controllers

- Open Host Controller Interface (**OHCI**)
 - USB 1.1 (12 Mbit/s)
- Universal Host Controller Interface (**UHCI**)
 - USB 1.1 (12 Mbit/s)
- Enhanced Host Controller Interface (**EHCI**)
 - USB 2.0 (480 Mbit/s)
- Extensible Host Controller Interface (**xHCI**)
 - USB 3.0, 3.1, 3.2 (5 Gbit/s, 10 Gbit/s, 20Gbit/s)



USB devices categories

- Human Interface Device (HID):
input devices (keyboard, mice, touchscreens, etc)
- Communication Devices: Modems, Network cards
- Mass Storage Devices: USB Hard Drives, USB Flash Drives, Memory cards
- Audio: Audio devices
- IrDA: Infrared devices
- USB Printers



Display USB devices with `lsusb`

- **\$ lsusb** # show USB buses and devices

Options:

- **-v** # verbose information for USB devices
- **-t** # show hierarchical topology of Usb buses and devices



Display USB devices with `lsusb`

- `$ lsusb # show USB buses and devices`

```
Bus 008 Device 001: ID 1d6b:0001 Linux Foundation 1.1 root hub
```

```
Bus 007 Device 001: ID 1d6b:0001 Linux Foundation 1.1 root hub
```

```
Bus 006 Device 001: ID 1d6b:0001 Linux Foundation 1.1 root hub
```

```
Bus 005 Device 001: ID 1d6b:0001 Linux Foundation 1.1 root hub
```

```
Bus 004 Device 002: ID 08ff:2810 AuthenTec, Inc. AES2810
```

```
Bus 004 Device 001: ID 1d6b:0001 Linux Foundation 1.1 root hub
```

```
Bus 003 Device 002: ID 093a:2510 Pixart Imaging, Inc. Optical Mouse
```

```
Bus 003 Device 001: ID 1d6b:0001 Linux Foundation 1.1 root hub
```

```
Bus 002 Device 002: ID 0951:1603 Kingston Technology DataTraveler  
1GB/2GB Pen Drive
```

```
Bus 002 Device 001: ID 1d6b:0002 Linux Foundation 2.0 root hub
```

```
Bus 001 Device 004: ID 17ef:1004 Lenovo
```

```
Bus 001 Device 001: ID 1d6b:0002 Linux Foundation 2.0 root hub
```




Display USB devices with `lsusb`

- ```
$ lsusb -t # show USB device topology
```

```
/: Bus 08.Port 1: Dev 1, Class=root_hub, Driver=uhci_hcd/2p, 12M
/: Bus 07.Port 1: Dev 1, Class=root_hub, Driver=uhci_hcd/2p, 12M
/: Bus 06.Port 1: Dev 1, Class=root_hub, Driver=uhci_hcd/2p, 12M
/: Bus 05.Port 1: Dev 1, Class=root_hub, Driver=uhci_hcd/2p, 12M
/: Bus 04.Port 1: Dev 1, Class=root_hub, Driver=uhci_hcd/2p, 12M
/: Bus 03.Port 1: Dev 1, Class=root_hub, Driver=uhci_hcd/2p, 12M
|__ Port 1: Dev 2, If 0, Class=HID, Driver=usbhid, 1.5M
/: Bus 02.Port 1: Dev 1, Class=root_hub, Driver=ehci_hcd/6p, 480M
/: Bus 01.Port 1: Dev 1, Class=root_hub, Driver=ehci_hcd/6p, 480M
|__ Port 6: Dev 4, If 0, Class='bInterfaceClass 0x0e not yet
handled', Driver=uvcvideo, 480M
|__ Port 6: Dev 4, If 1, Class='bInterfaceClass 0x0e not yet
handled', Driver=uvcvideo, 480M
```

# The PCI Bus

- The PCI Bus is used for connecting system extension cards
- These cards are Coldplug (The system needs to be off before they are plugged or unplugged)
- PCI-X: PCI Extended extension of PCI which is still compatible with traditional PCI
- PCI Express (PCIe) replaces PCI and PCI-X



# Display USB devices with `lspci`

- \$ **lspci** # show PCI controllers and devices

```
00:00.0 Host bridge: Intel Corporation Mobile 4 Series Chipset Memory Controller Hub (rev 07)
```

```
00:01.0 PCI bridge: Intel Corporation Mobile 4 Series Chipset PCI Express Graphics Port (rev 07)
```

```
00:03.0 Communication controller: Intel Corporation Mobile 4 Series Chipset MEI Controller (rev 07)
```

```
00:03.2 IDE interface: Intel Corporation Mobile 4 Series Chipset PT IDE Controller (rev 07)
```

```
00:03.3 Serial controller: Intel Corporation Mobile 4 Series Chipset AMT SOL Redirection (rev 07)
```

```
00:19.0 Ethernet controller: Intel Corporation 82567LM Gigabit Network Connection (rev 03)
```

```
00:1a.0 USB Controller: Intel Corporation 82801I (ICH9 Family) USB UHCI Controller #4 (rev 03)
```

```
00:1a.1 USB Controller: Intel Corporation 82801I (ICH9 Family) USB UHCI Controller #5 (rev 03)
```

# Display USB devices with `lspci`

## Options:

- **-t** # show hierarchical topology of controllers and devices
- **-v** # verbose information
- **-vv** # very verbose information
- **-vvv** # very very verbose information



# Kernel Modules

- Modules are object files that extend the functions of the Linux kernel
- They can be automatically or manually loaded or unloaded on demand
- They are used for device drivers, filesystems, protocols, etc
- They can be found under the directory:  
**\$ ls /lib/modules/\$(uname -r)**
- For legacy systems (kernel versions 2.4 and earlier), they have a **.o** extension
- For modern systems (kernel versions 2.6 and later), they have a **.ko** extension
  - In some systems (like CentOS) the modules are compressed with **xz** so they have a **ko.xz** extension
- **\$ find /lib/modules/\$(uname -r) -name "\*.ko" #** find all modules for version **\$(uname -r)**

# Module Configuration Files

- /etc/modules.conf # for kernel version 2.4
- /etc/modprobe.conf # for kernel 2.6 and above
- /etc/modprobe.d/\*.conf
- Modern systems use the **/etc/modprobe.d/\*.conf** format
- These files set different rules for the proper resolution of conflicts that arise because of dependencies
- For setting up modules to load on startup we can use these:
- /etc/modules
- /etc/modules-load.d/\*conf



# Show active modules with `lsmod`

- \$ lsmod # show loaded modules

| Module                                  | Size  | Used by                                                                 |
|-----------------------------------------|-------|-------------------------------------------------------------------------|
| nls_iso8859_1                           | 12713 | 1                                                                       |
| nls_cp437                               | 16991 | 1                                                                       |
| vfat                                    | 21708 | 1                                                                       |
| fat                                     | 61374 | 1 vfat                                                                  |
| usb_storage                             | 53538 | 1                                                                       |
| uas                                     | 17996 | 0                                                                       |
| xt_multiport                            | 12597 | 1                                                                       |
| iptable_filter                          | 12810 | 1                                                                       |
| ip_tables                               | 27456 | 1 iptable_filter # ←<br># iptables_filter<br># depends on<br># iptables |
| x_tables                                | 29581 | 3                                                                       |
| xt_multiport, iptable_filter, ip_tables |       |                                                                         |
| parport_pc                              | 36959 | 0                                                                       |
| ppdev                                   | 17113 | 0                                                                       |
| binfmt_misc                             | 17565 | 1                                                                       |
| joydev                                  | 17606 | 0                                                                       |



# Insert modules on a running kernel with `insmod`

- In legacy systems we simply use the module name:

```
insmod msdos
```

- In modern systems we have to define the exact path:

```
insmod /lib/modules/2.6.38-11-
generic/kernel/fs/fat/msdos.ko
```

- **insmod** does not load dependent modules. They have to be manually loaded in the correct order:

```
insmod fat ; insmod msdos
```

# Remove modules from a running kernel with `rmmmod`

- `$ rmmmod msdos # remove module  
msdos.ko from the running kernel`

## Options:

- `-a # remove all unused modules`



# Add/remove modules from a running kernel with `modprobe`

- The **modprobe** command is more powerful than **insmod** or **rmmmod** because it can load the called module as long as the modules it depends upon
- **\$ modprobe msdos** # this will add the **msdos.ko** modules as well as the **fat.ko** module, which is a dependency for **msdos.ko**
- **\$ modprobe -r msdos** # this will unload **msdos.ko**, along with **fat.ko**



# Add/remove modules from a running kernel with `modprobe`

## Options:

- **-a** # load all modules! Combined with **-t** it will load all modules of a certain category
- **-t <module category>** # successively load modules from a certain category until some one loads correctly, e.g. **-t net**.
- **-c** # show module configuration
- **-r** # remove module
- **-v** # verbose output



# Information about modules with `modinfo`

- \$ **modinfo msdos** # show information about msdos.ko

filename:

/lib/modules/4.9.0-6-amd64/kernel/fs/fat/msdos.ko

description: MS-DOS filesystem support

author: Werner Almesberger

license: GPL

alias: fs-msdos

depends: fat


retpoline: Y

intree: Y

vermagic: 4.9.0-6-amd64 SMP mod\_unload modversions



# License



The work titled "LPIC-1 101-500 – Lesson 9" by  
Theodosios Andreou is distributed with the  
Creative Commons Attribution ShareAlike 4.0  
International License.

