LPIC-1 102-400 – Lesson 15

109.2 Basic network configuration



Network Interfaces

- To connect a system to a network a Network Interface Card (NIC) is needed. A typical protocol used by these cards can Ethernet, Wi-Fi (wireless cards) and in legacy systems modems and RS-232 serial ports.
- Examples of network interfaces:
 - **lo (loopback)**: use to check the TCP/IP stack and for private access to local services. The localhost hostname and the 127.0.0.0/8 (IPv4) and ::1 (IPv6) IP addresses, point here
 - Legacy Device Naming:
 - eth0: The first Ethernet card starts from id 0. If there are more, this naming scheme increases the card id by 1 e.g. eth1, eth2 etc
 - wlan0: A Wi-Fi example
 - Consistent Network Device Naming:
 - **enp0s25**: an Ethernet example
 - **Wlp3s0**: a Wi-Fi example
 - **ppp0**: A modem example



Setting hostnames with /etc/hostname and /etc/hosts

- The /etc/hostname is used on most distros for setting up the hostname, e.g. web01. In RedHat systems the /etc/sysconfig/network file is used which contains the HOSTNAME variable e.g.: HOSTNAME=web01
- The hostname is also included in the /etc/hosts file:
 127.0.0.1 web01
- Often ot is combined with the domain name:
 127.0.0.1 web01.example.com web01



The 'hostname' command

- The **hostname** command can be used for setting and displaying the hostname and domainname
- \$ hostname # show hostname
 name-lpi
- \$ hostname -f # show host and domain name name-lpi.example.com
- # hostname other-name # change hostname.
 This change is temporary and the name
 will roll back on the next reboot unless
 we set the hostname in /etc/hostname
 and /etc/hosts



Associating hostnames with IP addresses in /etc/hosts

The /etc/hosts file is used to associate hostnames with IP addresses and it is a simple way to resolve hostnames in networks without DNS or in cases where you do not have access to the DNS server. You can also set easy to remember names for hosts you use often



Set name resolution systems with /etc/ nsswitch.conf

 The /etc/nsswitch.conf file configures the name resolution systems to be used and their priority that should be obeyed when resolving names of users, groups, password and hostnames

```
$ cat /etc/nsswitch.conf
passwd: files # resolve user names from /etc/passwd
shadow: files # resolve passwords from /etc/shadow
group: files # resolve group names from /etc/group
hosts: files dns # resolv hostnames from /etc/hosts and
then DNS
```



Set name resolution systems with /etc/ nsswitch.conf

- Othe possible authentication systems, instead of **ldap**, could be **nis** and **nisplus** of Sun Microsystems and **winbind** which can join a Linux system to Microsoft Active Directory



Configure a network interface with `ifconfig`

- The **ifconfig** command is used to configure a network interface and display network card settings. This configuration is not persistent!
- # ifconfig # show only active network interfaces

```
Link encap:Ethernet HWaddr 00:1c:25:9b:19:65
inet addr:192.168.2.10 Bcast:192.168.2.255
eth0
        Mask: 255.255.255.0
                                  inet6 addr: fe80::21c:25ff:fe9b:1965/64 Scope:Link
UP BROADCAST RUNNING MULTICAST MTU:1500 Metric:1
RX packets:5364 errors:0 dropped:0 overruns:0 frame:0
TX packets:5047 errors:0 dropped:0 overruns:0 carrier:0 collisions:0 txqueuelen:1000
RX bytes:5400323 (5.4 MB) TX bytes:785883 (785.8 KB)
Interrupt:20 Memory:fc200000-fc220000
10
                                   Link encap:Local Loopback inet addr:127.0.0.1 Mask:255.0.0.0
                                  inet6 addr: ::1/128 Scope:Host
UP LOOPBACK RUNNING MTU:16436 Metric:1
RX packets:260 errors:0 dropped:0 overruns:0 frame:0
TX packets:260 errors:0 dropped:0 overruns:0 carrier:0 collisions:0 txqueuelen:0
RX bytes:83809 (83.8 KB) TX bytes:83809 (83.8 KB)
```

Configure a network interface with `ifconfig`

- # ifconfig -a # show inactive interfaces as well
- # ifconfig eth0 # show eth0 network settings
- # ifconfig eth0 192.168.0.34 netmask 255.255.255.0 # set IP and netmask for eth0
- # ifconfig eth0 192.168.0.34 netmask 255.255.255.0 \
 broadcast 192.168.0.255 # set IP, netmask and broadcast address in eth0
- # ifconfig eth0 down # disable eth0
- # ifconfig eth0 up # enable eth0
- # ifconfig eth0 up 192.168.0.34 netmask 255.255.255.0 # configure the network interface and enable it at the same time



Persistent network settings with /etc/network/interfaces (Debian)

- In Debian systems the /etc/network/interfaces file is used for persistent network setup
- \$ cat /etc/network/interfaces auto lo iface lo inet loopback

auto eth0 <u>iface eth0 inet static # iface_eth0 inet</u>

address 10.0.2.15 netmask 255.255.255.0 network 10.0.2.0 broadcast 10.0.2.250 gateway 10.0.2.250 iface eth0 inet dhcp for automatic IP assignment

not needed for dhcp



Persistent network settings with /etc/sysconfig/network-scripts/ifcfg-ethX (RedHat)

 In RedHat systems, every network interface has its own configuration file under: /etc/sysconfig/network-scripts.

- \$ cat /etc/sysconfig/network-scripts/ifcfg-eth0
DEVICE=eth0
BOOTPROTO=none # =dhcp for automatic assignment
ONBOOT=yes
HWADDR=00:50:56:98:6e:d9
NETMASK=255.255.255.0
IPADDR=172.16.255.14
GATEWAY=172.16.255.250
TYPE=Ethernet



Enable/Disable network interfaces with `ifup` and `ifdown`

- The ifup and ifdown are used to enable and disable the network interfaces
- # ifdown eth0 # disable interface eth0
- # ifup eth0 # enable interface eth0



Configure static routing with `route`

- The route command is used to show the routing table and also for adding and removing static routes
- \$ route # show routing table with hostnames
- \$ route -n # show routing table numerically (IP Addresses)
- # route add default gw 10.0.2.2 eth0 # set 10.0.2.2 as default gateway
- # route add -net 10.200.0.0 netmask
 255.255.0.0 gw 10.10.250
 # set the 10.10.0.0/16 network over the
 10.10.10.250 gateway into the routing table
- # route del -host 10.5.4.6 netmask
 255.255.255.0 gw 172.16.1.1
 # delete host 10.5.4.6 with gateway
 172.16.1.1 from the routing table

Configure a Linux system as a router

- Most Linux systems are not set as a router. This means that if a
 packet arrives at an interface it cannot be forwarded from another
 interface
- # echo '1' > /proc/sys/net/ipv4/ip_forward # set IPv4 packet forwarding (non persistent)
- For a more persisten solution set the following variable in the /etc/sysctl.conf file: net.ipv4.ip_forward = 1



Configure network settings with 'ip'

- The ip command is a better replacement for the legacy ifconfig and route commands
- # ip addr # show interfaces with ip information

```
1: lo: <LOOPBACK, UP, LOWER_UP> mtu 65536 qdisc noqueue state UNKNOWN group default qlen 1000
    link/loopback 00:00:00:00:00:00 brd 00:00:00:00:00:00
    inet 127.0.0.1/8 scope host lo
        valid_lft forever preferred_lft forever
    inet6 ::1/128 scope host
        valid_lft forever preferred_lft forever

2: enp0s25: <BROADCAST, MULTICAST, UP, LOWER_UP> mtu 1500 qdisc
fq_codel state UP group default qlen 1000
    link/ether 28:d2:44:33:84:9c brd ff:ff:ff:ff:ff
    inet 192.168.10.225/24 brd 192.168.10.255 scope global dynamic
noprefixroute enp0s25
    valid_lft 38044sec preferred_lft 38044sec
    inet6 fd64:d180:8b30:0:2ad2:44ff:fe33:849c/64 scope global
dynamic mngtmpaddr
    valid_lft 6993sec preferred_lft 1593sec
    inet6 fe80::2ad2:44ff:fe33:849c/64 scope link
    valid_lft forever preferred_lft forever
```

Configure network settings with 'ip'

ip ro # show routing table

```
default via 192.168.10.1 dev enp0s25 proto dhcp metric 100 169.254.0.0/16 dev virbr0 scope link metric 1000 linkdown 192.168.10.0/24 dev enp0s25 proto kernel scope link src 192.168.10.225 metric 100 192.168.122.0/24 dev virbr0 proto kernel scope link src 192.168.122.1 linkdown
```



Configure network settings with 'ip'


- # ip addr add 192.168.1.7/24 dev enp0s2
 # set non-persistent IP address on
 enp0s2
- # ip addr del 192.168.1.7/24 dev enp0s2
 # delete IP address from enp0s2 (nonpersistent)
- # ip ro add default via 192.168.4.1 dev eno1 # set default gateway
- # ip ro add 192.168.5.0/24 via 192.168.5.1 dev enp0s3 # Add static route
- # ip link set wlp3s0 down # disable interface
- # ip link set wlp3s0 up # enable interface

The DHCP Protocol

- For the automatic assignment of IP addresses and the rest of the network configuration, the **DHCP** (Dynamic Host Configuration Protocol) protocol is used
- The DHCP protocols works on the client-server model. The computers set as DHCP clients send a broadcast message in the local network. If there is a DHCP server in the network it will reply with an available IP Address, the netmask, the Default Gateway, the DNS Servers and any other secondary configuration settings
- # dhclient eth0 # send a DHCP request from the eth0 interface



License



The work titled "LPIC-1 102-400 – Lesson 15" by Theodotos Andreou is distributed with the Creative Commons Attribution ShareAlike 4.0 International License.

